


DVD CAM Software Support Center

Software Tutorials


Driver Installation Manual: How to Install UDF driver

Installing UDF Device Driver


1. Terminate all the applications and insert the installation CD to the CD-ROM drive of your PC. If any anti-virus software is running, deactivate the software during the installation.
2. Use "My Computer" or "Windows Explorer" to open the folder in the CD called "IW", Instant Write, that is UDF driver software. Double-click Setup.exe to start installation. Refer to the screen shot as an example.



3. Follow the instructions on the dialog boxes appear on the screen. At Registration dialog box, type in "Name" and "Company" text boxes, otherwise; you wouldn't be able to go next. At Setup Complete dialog box, select "Yes, I want to restart my computer now" to restart.



4. To confirm whether "InstantWrite" is installed, check the software listed among "Add or Remove Programs" in Control Panel as below. Close.



- Cautions

- This UDF device driver 'InstantWrite' by VOB, has been developed for 12cm 4.7 GB DVD-RAM drive. Therefore, be sure not to use the following functions that appear with 'VOB InstantWrite' in the start menu when Hitachi DVD video camera/recorder is connected to PC.
 - InstantWrite Defrag
 - InstantWrite Format
- When initializing a DVD-RAM disc in Hitachi DVD video camera / recorder, be sure to use the "Format Disc" function built-in the Disc Navigation in Hitachi DVD video camera / recorder.
- The drive compression, defrag, and other disc utility programs for writing to the discs in Hitachi DVD video camera / recorder are not available
- A conflict with CD-R/RW software may occur and may cause CD-R/RW software or InstantWrite to behave abnormal.
- If the different UDF device driver has been pre-installed on your PC, there may be the conflict between InstantWrite and the other UDF driver. If you are using Hitachi DVD video camera / recorder connected to your PC, be sure to use InstantWrite as the UDF driver, otherwise; you may experience some problems.